

BIG-IP® Access Policy Manager®

Customization Guide

Version 11.2



IT agility. Your way.

Table of Contents

Legal Notices.....	7
Acknowledgments.....	9
Chapter 1: Overview of Customization.....	11
Overview: What is customization?.....	12
About the Customization tool.....	12
About customization views and form factors.....	12
Chapter 2: Configuring Settings in Basic Customization View.....	13
About Basic Customization view.....	14
Customizing Basic settings.....	14
Chapter 3: Personalizing Client Appearance in Advanced View.....	19
What is client personalization?.....	20
Adding images with the image browser.....	20
Personalizing client colors, logos, and icons.....	20
Previewing customization changes.....	21
Appearance properties for BIG-IP Edge Client.....	21
Localizing screen appearance for BIG-IP Edge Client.....	22
Previewing customization changes.....	22
Localization properties for BIG-IP Edge Client.....	22
Chapter 4: Personalizing Access Profile Appearance Settings.....	25
What is access profile personalization?.....	26
Personalizing page appearance for common access profile settings.....	26
Previewing customization changes.....	26
General page style settings for access profiles.....	27
Font settings for access profiles.....	27
Page header settings for access profiles.....	27
Page footer settings for access profiles.....	28
Layout settings for access profiles.....	28
Image settings for access profiles.....	29
Form settings for access profiles.....	29
Form element settings for access profiles.....	30
Advanced customization image settings.....	30
Personalizing page appearance for access profile logout settings.....	30
Advanced customization image settings.....	31

Table of Contents

Personalizing page appearance for access policy pages.....	31
Customization settings for access policy items.....	31
Localizing messages for BIG-IP Edge Client.....	32
Previewing customization changes.....	32
Customization settings for BIG-IP Edge Client localization.....	32
Chapter 5:	
Personalizing Webtop Appearance Settings in Advanced View.....	35
What is webtop appearance personalization?.....	36
Personalizing page appearance for webtops.....	36
Webtop network connectivity status icons settings.....	36
CSS sprite image setting.....	36
Web Applications Session Timeout settings.....	37
Web Applications Hometab settings.....	38
Full webtop settings.....	41
Full webtop popup window setting.....	42
Advanced customization image settings.....	42
Chapter 6: Personalizing Images for Resources in Advanced View.....	43
What is resource image personalization?.....	44
Personalizing resource images.....	44
Chapter 7: Localizing Messages and Images in Advanced View.....	45
What is full and mobile browser localization?.....	46
Localizing messages for common access profile settings.....	46
Localizing layout and content of the logon page.....	46
Framework installation settings.....	47
Endpoint security settings.....	48
Localizing layout and content of logout pages.....	50
Logout component settings.....	50
Localizing error messages.....	51
General error settings.....	51
AAA error settings.....	52
Installation error settings.....	53
Resource error settings.....	53
Dynamic configuration error settings.....	55
Other configuration error settings.....	55
Localizing logon pages.....	55
Logon page settings.....	55
Localizing decision pages.....	56
General decision page settings.....	56

Advanced customization image settings.....	57
Localizing message box pages.....	57
Advanced customization image settings.....	57
Localizing ending pages.....	58
Advanced customization image settings.....	58
Chapter 8: Localizing Webtops in Advanced View.....	59
What is webtop localization?.....	60
Localizing webtops.....	60
Webtop form and message settings.....	60
BIG-IP Edge Client webtop settings.....	62
Settings for showing and hiding information on webtops.....	63
Webtop logout and relaunch settings.....	63
Webtop activity section setting.....	63
Webtop new session settings.....	64
Webtop web applications session timeout settings.....	64
Webtop hometab settings.....	65
Full webtop settings.....	66
Full webtop popup window settings.....	67
Full webtop Citrix logon form settings.....	68
Full webtop Citrix installer settings.....	68
Full webtop Citrix browser setting.....	69
Chapter 9: Localizing Captions for Resources in Advanced View.....	71
What is resource caption localization?.....	72
Localizing captions.....	72
Chapter 10: Changing Customized Properties with Advanced Edit Mode.....	73
What is Advanced Edit Mode customization?.....	74
Editing files in Advanced Edit Mode.....	74

Table of Contents

Legal Notices

Publication Date

This document was published on May 7, 2012.

Publication Number

MAN-0387-01

Copyright

Copyright © 2012, F5 Networks, Inc. All rights reserved.

F5 Networks, Inc. (F5) believes the information it furnishes to be accurate and reliable. However, F5 assumes no responsibility for the use of this information, nor any infringement of patents or other rights of third parties which may result from its use. No license is granted by implication or otherwise under any patent, copyright, or other intellectual property right of F5 except as specifically described by applicable user licenses. F5 reserves the right to change specifications at any time without notice.

Trademarks

3DNS, Access Policy Manager, Acopia, Acopia Networks, Advanced Client Authentication, Advanced Routing, APM, Application Security Manager, ARX, AskF5, ASM, BIG-IP, Cloud Extender, CloudFucious, CMP, Data Manager, DevCentral, DevCentral [DESIGN], DNS Express, DSC, DSI, Edge Client, Edge Gateway, Edge Portal, EM, Enterprise Manager, F5, F5 [DESIGN], F5 Management Pack, F5 Networks, F5 World, Fast Application Proxy, Fast Cache, FirePass, Global Traffic Manager, GTM, IBR, Intelligent Browser Referencing, Intelligent Compression, IPv6 Gateway, iApps, iControl, iHealth, iQuery, iRules, iRules OnDemand, iSession, IT agility. Your way., L7 Rate Shaping, LC, Link Controller, Local Traffic Manager, LTM, Message Security Module, MSM, Netcelera, OneConnect, Packet Velocity, Protocol Security Module, PSM, Real Traffic Policy Builder, Scale^N, SSL Acceleration, StrongBox, SuperVIP, SYN Check, TCP Express, TDR, TMOS, Traffic Management Operating System, TrafficShield, Transparent Data Reduction, VIPRION, vCMP, WA, WAN Optimization Manager, WANJet, WebAccelerator, WOM, and ZoneRunner, are trademarks or service marks of F5 Networks, Inc., in the U.S. and other countries, and may not be used without F5's express written consent.

All other product and company names herein may be trademarks of their respective owners.

Patents

This product may be protected by U.S. Patent 7,114,180. This list is believed to be current as of May 7, 2012.

Export Regulation Notice

This product may include cryptographic software. Under the Export Administration Act, the United States government may consider it a criminal offense to export this product from the United States.

RF Interference Warning

This is a Class A product. In a domestic environment this product may cause radio interference, in which case the user may be required to take adequate measures.

Legal Notices

FCC Compliance

This equipment has been tested and found to comply with the limits for a Class A digital device pursuant to Part 15 of FCC rules. These limits are designed to provide reasonable protection against harmful interference when the equipment is operated in a commercial environment. This unit generates, uses, and can radiate radio frequency energy and, if not installed and used in accordance with the instruction manual, may cause harmful interference to radio communications. Operation of this equipment in a residential area is likely to cause harmful interference, in which case the user, at his own expense, will be required to take whatever measures may be required to correct the interference.

Any modifications to this device, unless expressly approved by the manufacturer, can void the user's authority to operate this equipment under part 15 of the FCC rules.

Canadian Regulatory Compliance

This Class A digital apparatus complies with Canadian ICES-003.

Standards Compliance

This product conforms to the IEC, European Union, ANSI/UL and Canadian CSA standards applicable to Information Technology products at the time of manufacture.

Acknowledgments

This product includes software developed by Bill Paul.

This product includes software developed by Jonathan Stone.

This product includes software developed by Manuel Bouyer.

This product includes software developed by Paul Richards.

This product includes software developed by the NetBSD Foundation, Inc. and its contributors.

This product includes software developed by the Politecnico di Torino, and its contributors.

This product includes software developed by the Swedish Institute of Computer Science and its contributors.

This product includes software developed by the University of California, Berkeley and its contributors.

This product includes software developed by the Computer Systems Engineering Group at the Lawrence Berkeley Laboratory.

This product includes software developed by Christopher G. Demetriou for the NetBSD Project.

This product includes software developed by Adam Glass.

This product includes software developed by Christian E. Hopps.

This product includes software developed by Dean Huxley.

This product includes software developed by John Kohl.

This product includes software developed by Paul Kranenburg.

This product includes software developed by Terrence R. Lambert.

This product includes software developed by Philip A. Nelson.

This product includes software developed by Herb Peyerl.

This product includes software developed by Jochen Pohl for the NetBSD Project.

This product includes software developed by Chris Provenzano.

This product includes software developed by Theo de Raadt.

This product includes software developed by David Muir Sharnoff.

This product includes software developed by SigmaSoft, Th. Lockert.

This product includes software developed for the NetBSD Project by Jason R. Thorpe.

This product includes software developed by Jason R. Thorpe for And Communications, <http://www.and.com>.

This product includes software developed for the NetBSD Project by Frank Van der Linden.

This product includes software developed for the NetBSD Project by John M. Vinopal.

This product includes software developed by Christos Zoulas.

This product includes software developed by the University of Vermont and State Agricultural College and Garrett A. Wollman.

This product includes software developed by Balazs Scheidler (bazsi@balabit.hu), which is protected under the GNU Public License.

Acknowledgments

This product includes software developed by Niels Mueller (nisse@lysator.liu.se), which is protected under the GNU Public License.

In the following statement, *This software* refers to the Mitsumi CD-ROM driver: This software was developed by Holger Veit and Brian Moore for use with 386BSD and similar operating systems. *Similar operating systems* includes mainly non-profit oriented systems for research and education, including but not restricted to NetBSD, FreeBSD, Mach (by CMU).

This product includes software developed by the Apache Group for use in the Apache HTTP server project (<http://www.apache.org/>).

This product includes software licensed from Richard H. Porter under the GNU Library General Public License (© 1998, Red Hat Software), www.gnu.org/copyleft/lgpl.html.

This product includes the standard version of Perl software licensed under the Perl Artistic License (© 1997, 1998 Tom Christiansen and Nathan Torkington). All rights reserved. You may find the most current standard version of Perl at <http://www.perl.com>.

This product includes software developed by Jared Minch.

This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>).

This product includes cryptographic software written by Eric Young (ey@cryptsoft.com).

This product contains software based on oprofile, which is protected under the GNU Public License.

This product includes RRDtool software developed by Tobi Oetiker (<http://www.rrdtool.com/index.html>) and licensed under the GNU General Public License.

This product contains software licensed from Dr. Brian Gladman under the GNU General Public License (GPL).

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).

This product includes Hypersonic SQL.

This product contains software developed by the Regents of the University of California, Sun Microsystems, Inc., Scriptics Corporation, and others.

This product includes software developed by the Internet Software Consortium.

This product includes software developed by Nominum, Inc. (<http://www.nominum.com>).

This product contains software developed by Broadcom Corporation, which is protected under the GNU Public License.

This product contains software developed by MaxMind LLC, and is protected under the GNU Lesser General Public License, as published by the Free Software Foundation.

Chapter 1

Overview of Customization

Topics:

- *Overview: What is customization?*
-

Overview: What is customization?

Customization allows you to provide users with a personalized experience for access policy screens, windows, and errors. Using the Customization tool, you can apply your organization's brand images and colors, change messages and errors for local languages, and change the layout of user pages and screens.

About the Customization tool

The Customization tool is an application that you start from the BIG-IP® admin console. With the Customization tool, you can personalize screen messages and prompts, change screen layouts, colors, and images, and customize error and other messages to specific languages for policies and profiles used on BIG-IP Access Policy Manager®.

Starting the Customization tool

Start the Customization tool to personalize and localize page layout, colors, images, and messages for the BIG-IP® Edge Client®, browser pages, and mobile device screens.

On the Main tab, click **Access Policy > Customization**.

The Customization tool appears, in Basic Customization view.

You can use the Customization tool inside the BIG-IP admin console, or click **Popout** to open it in a separate browser window.

After you personalize settings, remember to click the **Save** icon to apply your changes.

About customization views and form factors

The Customization tool provides two views:

- **Basic Customization (Quick Start)**: This is the default customization view. Use this to configure basic look and feel for pages, and common text labels and captions for resources on the webtop.
- **Advanced Customization (Advanced)**: This is the advanced customization view that provides a tree structure for configuration elements, and more detailed methods to configure and customize objects.

The Advanced Customization view provides two form factors, which you can use to customize different access policy features.

- **Full/Mobile browser**: Use this mode to configure pages that are viewed in a web browser or on a mobile device.
- **BIG-IP Edge Client**: Use this mode to configure the appearance and messages that appear in the BIG-IP® Edge Client® for a platform or device.

In addition, for each form factor you can choose to customize **Branding** or **Localization** by selecting the tab at the top of the Form Factor column.

- **Branding**: Customization controls the look of the user interface, such as fonts, images, colors, and general layout.
- **Localization**: Customization provides personalization for the text and messages that appear for each language specified in an access profile.

Chapter 2

Configuring Settings in Basic Customization View

Topics:

- [About Basic Customization view](#)
-

About Basic Customization view

You can use the Basic Customization view to configure common settings for access profile web pages, and the webtop captions, descriptions, and images for any item that appears on a full webtop. In addition, you can customize webtop font size and link colors.

With this view, you can customize:

- **Common Page Styles** - Specifies settings for the logon form display, header image, and alignment of items.
- **Webtop items** - Specifies settings for the display of resources (app tunnels, remote desktops, network access tunnels, webtop links, and portal access resources) on the full webtop.
- **Common webtop settings** - Specifies display settings that apply to all resources on the full webtop.
- **Webtop links** - Specifies display settings that apply to all resources on the full webtop.

Customizing Basic settings

Start Basic customization to configure custom settings for access profiles and items that appear on the full webtop. Basic customization provides a starting point that you can later refine through the Advanced Customization view.

1. From the Main tab, click **Access Policy > Customization > Quick Start**.
The Basic Customization view opens.
2. In the left column of the page, select the category of items to customize.
For example, select **Network Access** to customize the appearance of a network access resource item on the full webtop.
3. On the right-side of the page, from the list, select the specific item for which you want to customize settings.
The customizable settings for the item are displayed.
4. Configure settings for the resource item or access profile.
Click **Preview** to display your settings without saving your changes.

After you customize settings, click **Save** to save the new customization settings. To return to the original settings and discard your changes, click **Revert**.

Common page style settings

You can customize the following common page style settings for an access profile with the Basic view in the Customization tool. Select **Common Page Styles** to view these settings.

Name	Value	Description
Access Profile	An access profile already defined on the system	The access profile for which you want to change basic settings.
Language	A language already specified in the access profile on the system	This specifies the language for which you are changing customization settings. Select All languages to apply the same customization changes to all languages in the access profile.

Name	Value	Description
Form Left Margin	A numeric pixel value, or a percentage (for example, 10px or 5%)	The margin between the left edge of the form and the left edge of the browser window, on form-based pages.
Form Top Margin	A numeric pixel value or a percentage, (for example, 10px)	The margin between the top edge of the form and the bottom edge of the header image, on form-based pages.
Form Height	A numeric pixel value or a percentage, (for example, 500px or 50%)	The height of the form, on form-based pages. Any value less than the full height of the browser increases the space at the bottom of the form, as the top margin is set by the Form Top Margin value.
Form Background Color	A color, selected from a color chooser.	Indicates the color behind form-based pages.
Footer Text	A text string.	Specifies the footer message that appears at the bottom of access policy web pages.
Footer Font Size	Font size in pixels (for example 10px).	Indicates the size for the footer message at the bottom of access policy web pages.
Page Alignment	Left, center, or right	Sets the alignment of the page within the web browser window.
Page Width	Pixel or percentage value (for example 90%)	The width of any access policy web pages inside the web browser frame.
Header Logo	An image	The header logo appears, by default, at the upper-left corner of the defined HTML page. Typically this is a square, transparent image file. Acceptable formats for transparency are GIF and PNG. The page header area expands to the height of this image.

App tunnel basic settings

You can customize the following settings for an app tunnel on the full webtop, with the Basic view in the Customization tool. Select **App Tunnel** to view these settings.

Name	Value	Description
App Tunnel	An app tunnel already defined on the system	The app tunnel for which you want to change basic settings.
Language	A language already specified on the system	This specifies the language for which you are changing customization settings. Select All languages to apply the same customization changes to all languages in the access profile.
Caption	A text string	The text under the icon for the app tunnel, on a full webtop.
Description	A text string	The description text for the app tunnel, on a full webtop.
Image	An image or icon	The image acts as an icon on the full webtop to represent the app tunnel. Select an image from the list, or click Upload New Image to add a new image.

Configuring Settings in Basic Customization View

Network access basic settings

You can customize the following settings for a network access resource on the full webtop, with the Basic view in the Customization tool. Select **Network Access** to view these settings.

Name	Value	Description
Network Access	A network access resource already defined on the system	The network access resource for which you want to change basic settings.
Language	A language already specified on the system	This specifies the language for which you are changing customization settings. Select All languages to apply the same customization changes to all languages in the access profile.
Caption	A text string	The text under the icon for the network access resource, on a full webtop.
Description	A text string	The description text for the network access resource, on a full webtop.
Image	An image or icon	The image acts as an icon on the full webtop to represent the network access resource. Select an image from the list, or click Upload New Image to add a new image.

Remote desktop basic settings

You can customize the following settings for a remote desktop on the full webtop, with the Basic view in the Customization tool. Select **Remote Desktop** to view these settings.

Name	Value	Description
Network Access	A remote desktop already defined on the system	The remote desktop for which you want to change basic settings.
Language	A language already specified on the system	This specifies the language for which you are changing customization settings. Select All languages to apply the same customization changes to all languages in the access profile.
Caption	A text string	The text under the icon for the remote desktop, on a full webtop.
Description	A text string	The description text for the remote desktop, on a full webtop.
Image	An image or icon	The image acts as an icon on the full webtop to represent the remote desktop. Select an image from the list, or click Upload New Image to add a new image.

Common webtop settings

You can customize the following shared settings for full webtops, with the Basic view in the Customization tool. Select **Common Webtop Settings** to view these settings.

Name	Value	Description
Webtop	A webtop already defined on the system	The webtop for which you want to change basic settings.
Language	A language already specified on the system	This specifies the language for which you are changing customization settings. Select All languages to apply the same customization changes to all languages in the access profile.
Font size	A pixel value, (for example 14px)	The font size used for text on the full webtop.
Link color	A color, selected from a color chooser	Indicates the color for links on the webtop.
Image	An image or icon	The image appears on the full webtop. Select an image from the list, or click Upload New Image to add a new image.

Webtop link basic settings

You can customize the following settings for a webtop link on the full webtop, with the Basic view in the Customization tool. Select **Portal Access** to view these settings.

Name	Value	Description
Webtop link	A webtop link already defined on the system	The webtop link for which you want to change basic settings.
Language	A language already specified on the system	This specifies the language for which you are changing customization settings. Select All languages to apply the same customization changes to all languages in the access profile.
Caption	A text string	The text under the icon for the webtop link, on a full webtop.
Description	A text string	The description text for the webtop link, on a full webtop.
Image	An image or icon	The image acts as an icon on the full webtop to represent the webtop link. Select an image from the list, or click Upload New Image to add a new image.

Portal access resource basic settings

You can customize the following settings for a portal access resource on the full webtop, with the Basic view in the Customization tool. Select **Portal Access** to view these settings.

Name	Value	Description
Portal Access	A portal access resource already defined on the system	The portal access resource for which you want to change basic settings.
Language	A language already specified on the system	This specifies the language for which you are changing customization settings. Select All languages to apply the

Configuring Settings in Basic Customization View

Name	Value	Description
		same customization changes to all languages in the access profile.
Caption	A text string	The text under the icon for the portal access resource, on a full webtop.
Description	A text string	The description text for the portal access resource, on a full webtop.
Image	An image or icon	The image acts as an icon on the full webtop to represent the portal access resource. Select an image from the list, or click Upload New Image to add a new image.

Chapter

3

Personalizing Client Appearance in Advanced View

Topics:

- *What is client personalization?*
- *Adding images with the image browser*
- *Personalizing client colors, logos, and icons*
- *Localizing screen appearance for BIG-IP Edge Client*

What is client personalization?

To personalize client pages, you use BIG-IP® Edge Client® customization. You can change the branding and localization of the BIG-IP Edge Client on client PCs and devices.

Adding images with the image browser

You can add images to Access Policy Manager® with the image browser. You can then select and use these images by means of settings within the Customization tool.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. On the top pane of the Customization tool, click **Image Browser**.
The image browser opens in a new window.
4. Select the image filter method from the **Filter Messages** list.
 - Select **Default Images** to view the included default Access Policy Manager images.
 - Select **User Uploaded Images** to view the custom uploaded images.
5. Add and remove images.
 - To add an image, click **Add Image**, select the image, and click **Open**.
 - To remove an image, select the image in the image browser, and click **Delete Image**.

Personalizing client colors, logos, and icons

In a connectivity profile, you can customize the appearance of the BIG-IP® Edge Client® and the web client. The settings you specify are saved with the connectivity profile, and applied when users download the client package.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **BIG-IP Edge Client**.
4. Under **Form Factor: BIG-IP Edge Client**, select the **Branding** tab.
5. Expand the folders in the Customization tool navigation pane to select the BIG-IP Edge Client in **Customization Settings > Connectivity Profiles > *name_of_connectivity_profile* > BIG-IP Edge Client**.
6. Customize the settings for BIG-IP Edge Client branding.
7. After you customize settings, click the **Save** icon at the top of the Customization tool.

Previewing customization changes

You must have customized an element with the Customization tool to see a preview of your changes.

After you customize and save an element with the Customization tool, you can preview the changes you have made in the Preview window. The Preview window opens a separate browser window, and shows a live update of changes as you save them.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. At the top of the Customization tool, click the **Preview** button.
4. Navigate to a page to view customizations. For example, to navigate to a login page and view the results of access profile branding customization, in the Preview window, expand **Customization Settings > Access Profiles > access_profile_name > Access Policy > Logon Pages > logon_page_name**.

The Preview window shows the results of any customization changes.

Appearance properties for BIG-IP Edge Client

You can customize the following appearance settings for BIG-IP® Edge Client® with the Customization tool.

Name	Value	Description
Banner Color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Indicates the color that the banner for the BIG-IP Edge Client uses. Note that the Banner Text Color should be legible over this color.
Banner Text Color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Indicates the color in which the banner text appears. This color appears over the Banner Color and should be readable on it.
Logo	A 48 x 48 PNG, JPG, or GIF icon.	This logo appears in the BIG-IP Edge Client as the company logo. The generic logo is an F5 logo. To change the logo, click the logo popout button, then click Replace . Select an image file to replace the logo file. Note that you can add files to the Customization tool in the image browser.
Tray Icon Set	The F5 tray logo set or the generic icon set.	Select the setting that will appear in the system tray to show connection activity and status. You can choose the F5 icon set (red ball), or a Generic icon set.

Localizing screen appearance for BIG-IP Edge Client

Configure localization for BIG-IP® Edge Client® to change the messages and text in the BIG-IP Edge Client application.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **BIG-IP Edge Client**.
4. Under **Form Factor: BIG-IP Edge Client** select the **Localization** tab.
5. Expand the folders in the Customization tool navigation pane to select the BIG-IP Edge Client in **Customization Settings > Connectivity Profiles > *name_of_connectivity_profile* > BIG-IP Edge Client**.
6. At the top right-side of the customization settings pane, select the **Language** for which to customize localization messages for the BIG-IP Edge Client.
7. Customize the settings for BIG-IP Edge Client localization.
8. After you customize settings, click the **Save** icon at the top of the Customization tool.

Previewing customization changes

You must have customized an element with the Customization tool to see a preview of your changes.

After you customize and save an element with the Customization tool, you can preview the changes you have made in the Preview window. The Preview window opens a separate browser window, and shows a live update of changes as you save them.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. At the top of the Customization tool, click the **Preview** button.
4. Navigate to a page to view customizations. For example, to navigate to a login page and view the results of access profile branding customization, in the Preview window, expand **Customization Settings > Access Profiles > *access_profile_name* > Access Policy > Logon Pages > *logon_page_name***.

The Preview window shows the results of any customization changes.

Localization properties for BIG-IP Edge Client

You can customize the following settings for BIG-IP® Edge Client® customization with the Customization tool.

Name	Value	Description
About link	A URL	The text that appears as a link in the About area of the BIG-IP Edge Client.

Name	Value	Description
About text	Text	Text, typically copyright info or some other identifying information, that appears in the About area of the BIG-IP Edge Client.
Application Name	Text	The application name, which appears in the status bar of the application.

Personalizing Client Appearance in Advanced View

Chapter 4

Personalizing Access Profile Appearance Settings

Topics:

- *What is access profile personalization?*
- *Personalizing page appearance for common access profile settings*
- *Personalizing page appearance for access profile logout settings*
- *Personalizing page appearance for access policy pages*
- *Localizing messages for BIG-IP Edge Client*

What is access profile personalization?

With full and mobile browser customization, you can change the appearance, text, and messages of all pages that a browser views, either from the BIG-IP® Edge Client® by directly logging in through a web browser, or on a mobile device. Some settings that are specific to the BIG-IP Edge Client software are customized separately in the BIG-IP Edge Client customization view.

Personalizing page appearance for common access profile settings

Personalize access profile login pages to change the front image and advanced customization images for the login page in a specific access policy.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Under **Form Factor: Full/Mobile Browser**, select the Branding tab.
5. Expand the folders in the Customization tool to customize settings. Navigate to **Customization Settings > Access Profiles > *access_profile_name* > Common** to configure common settings.
6. Customize the settings for each individual element by clicking on the element and changing the displayed settings.
7. After you customize settings, click the **Save** icon at the top of the Customization tool.

The access policy login page reflects your changes.

Previewing customization changes

You must have customized an element with the Customization tool to see a preview of your changes.

After you customize and save an element with the Customization tool, you can preview the changes you have made in the Preview window. The Preview window opens a separate browser window, and shows a live update of changes as you save them.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. At the top of the Customization tool, click the **Preview** button.
4. Navigate to a page to view customizations. For example, to navigate to a login page and view the results of access profile branding customization, in the Preview window, expand **Customization Settings > Access Profiles > *access_profile_name* > Access Policy > Logon Pages > *logon_page_name***.

The Preview window shows the results of any customization changes.

General page style settings for access profiles

You can customize the following settings for general page style with the Customization tool.

Name	Value	Description
Page alignment	Left, center, or right.	Indicates the general HTML page alignment for all pages displayed by the access profile.
Page background color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Indicates the color for the general page background for all pages displayed by the access profile.
Page width (px or %)	A specific pixel value, for example 800px, or a percentage, for example 80%.	Specifies the width of the content on all HTML pages displayed by the access profile, as an absolute pixel value or as a percentage of the entire browser screen.

Font settings for access profiles

You can customize the following settings for general page style with the Customization tool.

Name	Value	Description
Font family (comma-separated)	Font names or font-family names, space-separated, for example Calibri, Tahoma, Verdana, Arial, Helvetica, Sans-Serif.	Specifies the base font used by pages displayed by the access profile.
Headline font size (px)	A pixel value, for example 18px.	Indicates the pixel size for heading items on pages displayed by the access profile.
Text font size (px)	A pixel value, for example 14px.	Indicates the pixel size for text items on pages displayed by the access profile.

Page header settings for access profiles

You can customize the following settings for the page header style with the Customization tool.

Name	Value	Description
Disconnect icon	An image icon 48 x 48 pixels or smaller.	Specifies the icon image displayed in the browser when the page is disconnected.
Header background color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and	Indicates the background color for HTML header elements for the web pages served to web and mobile clients.

Personalizing Access Profile Appearance Settings

Name	Value	Description
	the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	
Header left image (Full Size)	An image name. This is a larger image up to 80 x 80 pixels, for display on web pages.	The header image for web pages. To replace this image, type the relative path, or click the preview icon to the right of the filename, and click Replace .
Header left image (Mobile Devices Size)	An image name. This is a smaller image up to 32 x 32 pixels, for display on mobile devices.	The header image for mobile device pages. To replace this image, type the relative path, or click the preview icon to the right of the filename, and click Replace .

Page footer settings for access profiles

You can customize the following settings for the page footer style with the Customization tool.

Name	Value	Description
Footer font size (px)	A font size, in pixels, for example 12px.	Specifies the font size for text in web page footers.

Layout settings for access profiles

You can customize the following settings for page layouts with the Customization tool.

Name	Value	Description
Form cell width (px or %)	Width, in pixels or percentage, of the main login page form, for example 240px, or 50%.	Specifies the width of the login page form in pixels or as a percentage of the frame.
Image cell width (px or %)	Width, in pixels or percentage, of the main login page image cell width, for example 240px, or 50%.	Specifies the width of the login page image area in pixels or as a percentage of the frame.
Main table background color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Indicates the background color for the login page main frame.
Page layout	Form left, form center, or form right.	Indicates the placement of the login page form on the main access policy page.

Image settings for access profiles

You can customize the following settings for the main page image with the Customization tool.

Name	Value	Description
Default image	Width, in pixels or percentage, of the main login page form, for example 240px, or 50%.	Specifies the width of the login page form in pixels or as a percentage of the frame.
Image left margin (px)	Left side margin, in pixels, of the main login page image, for example 24px.	Specifies the left margin of the login page image.
Image right margin (px)	Right side margin, in pixels, of the main login page image, for example 24px.	Specifies the right margin of the login page image.
Image top margin (px)	Top-edge margin, in pixels, of the main login page image, for example 24px.	Specifies the top margin of the login page image.
Side image alignment	Center, left, or right.	Specifies the alignment of the image within the side frame.

Form settings for access profiles

You can customize the following settings for the login form with the Customization tool.

Name	Value	Description
Form alignment	Center, left, or right.	Specifies the alignment of the form within the form frame.
Form background color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Indicates the background color for the login page form.
Form height (px, %, or auto)	Height value in pixels, as a percentage of the frame, or auto, for example 240px, 40%, or auto.	Specifies the height of the login form in the login frame.
Form left margin (px)	Left margin, in pixels, of the main login page form, for example 24px.	Specifies the left margin of the login form.
Form right margin (px)	Right margin, in pixels, of the main login page form, for example 24px.	Specifies the right margin of the login form.
Form top margin (px)	Top margin, in pixels, of the main login page form, for example 24px.	Specifies the top margin of the login form.
Form width (px or %)	Form width in pixels or as a percentage of the form frame, for example 250px or 50%.	Specifies the login form width within the login frame.

Form element settings for access profiles

You can customize the following settings for the appearance of elements in the login form with the Customization tool.

Name	Value	Description
Field alignment	Center, left, or right.	Specifies how fields align in the login form.
Field width (%)	A percentage value, for example 67%.	Specifies the width of fields in the login form, as a percentage of the total size of the login form.
Header alignment	Left, center, or right.	Specifies the alignment of header elements in the login form.
Label alignment	Left, center, or right.	Specifies the alignment of form field labels in the login form.
Label position	Left or above.	Specifies whether login form field labels are above or to the left of their respective fields.
Label width (%)	A percentage value, for example 67%.	Specifies the width of field labels in the login form.

Advanced customization image settings

You set advanced customization images to make images you add through the image browser available to your advanced customization pages.

The **Advanced Customization Images** properties pages allow you to set advanced customization images from the image browser to associate with advanced customization image names. You can then use the image name to add an image to an advanced customization page.

To select an image from the image browser to associate with an image for advanced customization, click the button next to the current (or default) image name, and select **Replace**.

Personalizing page appearance for access profile logout settings

Personalize access profile logout settings to add advanced customization image support to logout pages in the access profile.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Under **Form Factor: Full/Mobile Browser**, select the Branding tab.
5. Expand the folders in the Customization tool to customize settings. Navigate to **Customization Settings > Access Profiles > access_profile_name > Logout** to configure logout settings.
6. Customize the settings for advanced customization images.

- After you customize settings, click the **Save** icon at the top of the Customization tool.

The access policy advanced customization page reflects your changes.

Advanced customization image settings

You set advanced customization images to make images you add through the image browser available to your advanced customization pages.

The **Advanced Customization Images** properties pages allow you to set advanced customization images from the image browser to associate with advanced customization image names. You can then use the image name to add an image to an advanced customization page.

To select an image from the image browser to associate with an image for advanced customization, click the button next to the current (or default) image name, and select **Replace**.

Personalizing page appearance for access policy pages

Personalize access policy pages to change advanced customization images for the login page in a specific access policy, and to add advanced customization images for other access policy pages.

- On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
- In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
- Under **Form Factor: Full/Mobile Browser**, select the Branding tab.
- Expand the folders in the Customization tool to customize settings. Navigate to **Customization Settings > Access Profiles > *access_profile_name* > Access Policy**, and select the folder of the item to customize.
- Customize the settings for each individual element by clicking on the element and changing the displayed settings.
- After you customize settings, click the **Save** icon at the top of the Customization tool.

The access policy pages reflect your changes.

Customization settings for access policy items

You can personalize the following settings for pages exposed to the user in an access policy.

Name	Value	Description
General > Front image	Image	The image that appears in the image frame of the login page for an access policy.
Advanced Customization Images	Images	Each Advanced Customization Images properties page allows you to set advanced customization images from the image browser to associate with advanced customization image names. Each access policy item has a page for advanced customization images. You can use these image names to add an image to a page using advanced customization. To select an image from the image browser to associate with an image for advanced customization, click the button next to the current (or default) image name, and select Replace .

Localizing messages for BIG-IP Edge Client

Configure localization for BIG-IP® Edge Client® to change the messages and text in the BIG-IP Edge Client application.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **BIG-IP Edge Client**.
4. Expand the folders in the Customization tool navigation pane to select the BIG-IP Edge Client in **Customization Settings > Connectivity Profiles > *name_of_connectivity_profile* > BIG-IP Edge Client**.
5. At the top right-side of the customization settings pane, select the **Language** for which to customize localization messages for the BIG-IP Edge Client.
6. Customize the settings for BIG-IP Edge Client localization.
7. After you customize settings, click the **Save** icon at the top of the Customization tool.

Previewing customization changes

You must have customized an element with the Customization tool to see a preview of your changes.

After you customize and save an element with the Customization tool, you can preview the changes you have made in the Preview window. The Preview window opens a separate browser window, and shows a live update of changes as you save them.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. At the top of the Customization tool, click the **Preview** button.
4. Navigate to a page to view customizations. For example, to navigate to a login page and view the results of access profile branding customization, in the Preview window, expand **Customization Settings > Access Profiles > *access_profile_name* > Access Policy > Logon Pages > *logon_page_name***.

The Preview window shows the results of any customization changes.

Customization settings for BIG-IP Edge Client localization

You can customize the following settings for BIG-IP® Edge Client® customization with the Customization tool.

Name	Value	Description
About link	A URL	The text that appears as a link in the about area of the BIG-IP Edge Client.

Name	Value	Description
About text	Text	Text, typically copyright info or some other identifying information, that appears in the about area of the BIG-IP Edge Client.
Application Name	Text	The application name, which appears in the status bar of the application.

Personalizing Access Profile Appearance Settings

Chapter 5

Personalizing Webtop Appearance Settings in Advanced View

Topics:

- [What is webtop appearance personalization?](#)
- [Personalizing page appearance for webtops](#)

What is webtop appearance personalization?

You can customize the appearance of a webtop, including the layout of the webtop screen, images, and colors associated with the webtop.

Personalizing page appearance for webtops

Personalize webtop appearance settings to change the appearance and layout of specific webtops.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Under **Form Factor: Full/Mobile Browser** select the Branding tab.
5. Expand the folders in the Customization tool to customize settings.
6. Navigate to **Customization Settings > Webtops > *webtop_name***.
7. Customize the settings for each individual element by clicking on the element and changing the displayed settings.
8. After you customize settings, click the **Save** icon at the top of the Customization tool.

The webtop pages display your changes.

Webtop network connectivity status icons settings

You can customize the following icons for connectivity status on the webtop.

Name	Value	Description
Connected icon	16x16px image	Specifies the image for the connected status light on the webtop.
Disconnected icon	16x16px image	Specifies the image for the disconnected status light on the webtop.
Waiting icon	32x32px image	Specifies the image that displays while the client is connecting.

CSS sprite image setting

You can specify the portal access connection CSS sprites image with this setting.

Name	Value	Description
CSS Sprites image	An image file	Specifies the image to use for sprites to construct the webtop windows.

Web Applications Session Timeout settings

Portal access timeouts cause special behavior on the portal access webtop screen. When the session reaches the session timeout guard time, BIG-IP® Access Policy Manager® displays a session timeout warning, and dims the screen behind the warning. Depending on the type of timeout, the user sees different choices. You can use the following options to customize and configure session timeout options.

Name	Value	Description
'Inactivity Timeout' background color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Specifies the color of the background that appears behind the session timeout warning pop-up screen, when the timeout occurs because the session is inactive.
'Maximum Session Timeout' background color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Specifies the color of the background that appears behind the session timeout warning pop-up screen, when the timeout occurs because the session has reached the maximum timeout.
Dialog background color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Indicates the page background color for the timeout dialog box presented by session inactivity timeouts or maximum session timeouts.
Dialog x-size in pixels	Number (px)	Specifies the width, in pixels, of the timeout dialog.
Dialog y-size in pixels	Number (px)	Specifies the height, in pixels, of the timeout dialog.

Personalizing Webtop Appearance Settings in Advanced View

Name	Value	Description
Dimmed opacity percentage	Number (1-100)	Specifies the opacity of the background that appears behind the session timeout warning pop-up screen.
Guard time	Number (seconds)	Specifies the number of seconds before timeout that the session timeout warning pop-up screen appears.
Position of buttons Background image (hover) in CSS Sprites image	Coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the button background image that appears when the mouse hover.
Position of buttons Background image in CSS Sprites image	Coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the button background image.
Position of header Background image in CSS Sprites image	Coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the background hover image.
Position of Left Sidepart image (hover) in CSS Sprites image	Coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the left-side mouse hover image.
Position of Left Sidepart image in CSS Sprites image	Coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the left-side image.
Position of Logout image in CSS Sprites image	Coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the logout image.
Position of Right Sidepart image (hover) in CSS Sprites image	Coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the right-side hover image.
Position of Right Sidepart image in CSS Sprites image	Coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the right-side image.
Position of Warning image in CSS Sprites image	Coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the warning image.

Web Applications Hometab settings

Portal access connections include an optional hometab, which provides buttons and links for working with portal access and a URL bar. You can customize and configure the hometab with the following options.

Name	Value	Description
Data entry background color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color	Specifies the color of the background that appears behind the data entry fields on the hometab.

Name	Value	Description
	from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	
Data entry left and right border color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Specifies the color of the borders for the data entry area.
Data entry text color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Specifies the text color for data entry fields.
Font size (px)	pixel value (for example, 14px)	Specifies the font size on the hometab.
Link color	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Specifies the link text color on the hometab.
Link color (hover)	A hex color code, for example, #123ABC. When you click the color value, two color choosers appear. One allows you to select a color from 40 common color blocks, and the other allows you to select any HTML color from a more sophisticated color wheel. You can also type the color value in as text.	Specifies the color for links when the mouse hovers over them.
Position of Background image (hover) in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the background image that appears when the mouse hovers.

Personalizing Webtop Appearance Settings in Advanced View

Name	Value	Description
Position of Background image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the background image.
Position of divider image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the divider image.
Position of home image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the Home image.
Position of Left Sidepart image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the left side image.
Position of Logout image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the logout image.
Position of Open-In-New-Window image (hover) in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the "open in new window" image, when the mouse hovers over it.
Position of Open-In-New-Window image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the "open in new window" image.
Position of Reduced toolbar image (hover) in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the minimized toolbar image, when the mouse hovers over it.
Position of Reduced toolbar image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the minimized toolbar image.
Position of Right Sidepart image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the right side image.
Position of Shrink image (hover) in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the shrink image, when the mouse hovers over it.
Position of Shrink image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the shrink image.
Position of Transparent background image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the warning image.

Name	Value	Description
Position of Transparent sidepart image in CSS Sprites image	coordinates in px (-left, -top)	Specifies the offset from the left and top margin of the CSS Sprites image for the transparent side image.
Set of elements to be displayed	comma-separated list	<p>This is a comma-separated list of all the elements displayed on the hometab. The hometab is arranged in the order in which you specify these elements. Elements can be used more than once. The default specification is <code>shrink,divider,home,url,logout</code>.</p> <p>You can specify the following elements for the home tab:</p> <ul style="list-style-type: none"> shrink Specifies the hometab shrink element. divider Specifies a hometab field separator element. url Specifies the hometab URL box element. home Specifies the home link and text element. logout Specifies the logout link and image element.

Full webtop settings

You can configure the appearance of the full webtop with these settings.

Name	Value	Description
Header message icon	Image	Specifies the image for the header message icon on the full webtop. To change the image, click the image popout button at the right of the field, then click Replace . Select an image file to replace the image file. Note that you can add files to the Customization tool in the image browser.
Help window logo	Image	Specifies the image that a webtop user can click to open the webtop online help. To change the image, click the image popout button at the right of the field, then click Replace . Select an image file to replace the image file. Note that you can add files to the Customization tool in the image browser.
Toolbar - go icon	Image	Specifies the image that a user clicks to go to a site from the webtop toolbar. To change the image, click the image popout button at the right of the field, then click Replace . Select an image file to replace the image file. Note that you can add files to the Customization tool in the image browser.
Toolbar - help icon	Image	Specifies the image that a user clicks to open the help from the webtop toolbar. To change the image, click the image popout button at the right

Personalizing Webtop Appearance Settings in Advanced View

Name	Value	Description
		of the field, then click Replace . Select an image file to replace the image file. Note that you can add files to the Customization tool in the image browser.

Full webtop popup window setting

You can add the company logo to the full webtop with this setting.

Name	Value	Description
Company logo	Image	Specifies the image for the company logo on the full webtop. To change the image, click the image popout button at the right of the field, then click Replace . Select an image file to replace the image file. Note that you can add files to the Customization tool in the image browser.

Advanced customization image settings

You set advanced customization images to make images you add through the image browser available to your advanced customization pages.

The **Advanced Customization Images** properties pages allow you to set advanced customization images from the image browser to associate with advanced customization image names. You can then use the image name to add an image to an advanced customization page.

To select an image from the image browser to associate with an image for advanced customization, click the button next to the current (or default) image name, and select **Replace**.

Chapter

6

Personalizing Images for Resources in Advanced View

Topics:

- *What is resource image personalization?*
- *Personalizing resource images*

What is resource image personalization?

With image personalization, you can change the image displayed for a resource on the webtop.

Personalizing resource images

Personalize webtop resource images to provide customized icons on the full webtop for resources.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Click the **Branding** tab.
5. Select the resource type folder for **App Tunnels, Network Access, Remote Desktops, Portal Access, or Webtop Links**.
6. Select the resource name.
7. At the top right of the customization settings pane, select the **Language** for which to customize the caption and description for full and mobile browsers.
8. In the **Image** area, click the icon at the right of the field to show the current icon, then click **Replace** and select a new image.
9. After you customize settings, click the **Save** icon at the top of the Customization tool.

Chapter 7

Localizing Messages and Images in Advanced View

Topics:

- *What is full and mobile browser localization?*
- *Localizing messages for common access profile settings*
- *Localizing layout and content of the logon page*
- *Localizing layout and content of logout pages*
- *Localizing error messages*
- *Localizing logon pages*
- *Localizing decision pages*
- *Localizing message box pages*
- *Localizing ending pages*

What is full and mobile browser localization?

With localization, you can change the text and messages for web browsers and mobile clients for any language defined in an access profile. The Customization tool provides a tree view that you can use to navigate through the hierarchy of access profile items, in order to localize messages.

Localizing messages for common access profile settings

Localize common access profile pages to configure headers, footers, and standard warnings and text messages for a specific language.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Expand the folders in the Customization tool navigation pane to select page header settings, page footer settings, and other settings: **Customization Settings > Access Profiles > name_of_access_profile > Common**.
5. At the top right-side of the customization settings pane, select the **Language** for which to customize localization messages for full and mobile browsers.
6. Click **Page Header Settings** to provide a customized disconnection message.
7. Click **Page Footer Settings** to provide a customized footer for access profile pages.
8. Click **Other Settings** to configure the following settings.

Options	Description
JavaScript® disabled warning	Specifies the warning when JavaScript is not enabled in the browser.
New session link	Specifies the link text to start a new session.
New session text	Specifies the text that appears before the new session link.

9. After you customize settings, click the **Save** icon at the top of the Customization tool.

Localizing layout and content of the logon page

Customize the layout and content of components that appear on the logon page when the access policy is starting by customizing the framework pages.



Note: Use an HTML editor to edit the HTML code for the framework installation. The code appears unformatted and without line breaks in the Customization tool.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Expand the folders in the Customization tool navigation pane to select the framework installation item: **Customization Settings > Access Profiles > *name_of_access_profile* > Framework Installation**.
5. At the top right of the customization settings pane, select the **Language** for which to customize localization messages for full and mobile browsers.
6. Customize the settings for the logon page elements.
7. After you customize settings, click the **Save** icon at the top of the Customization tool.

Framework installation settings

You can customize the following settings for general page style with the Customization tool.

Name	Value	Description
ActiveX install options screen	Formatted HTML text	Specifies the page text and links that prompt a user to install a new ActiveX® browser component. This screen appears for Windows® Internet Explorer® users only.
Allow browser plugin install screen	Formatted HTML text	Specifies the page text and links displayed when the user's browser does not currently allow software installation. This page contains information about how to enable software installation, and links to continue to install plug-ins or to continue without installing the browser plug-ins.
Allow browser plugin install screen (Linux)	Formatted HTML text	Specifies the page text and links displayed when the user's browser does not currently allow software installation. This page contains information about how to enable software installation, and links for continuing to install plug-ins or to continue without installing the browser plug-ins. This screen appears for Linux® operating systems and browsers.
Browser plugin install with manual install options screen	Formatted HTML text	Specifies the page text and links that prompt a user to install a new browser plug-in component. This screen provides manual download and installation options. This screen appears for most operating systems and browsers.
Browser plug-in install with manual install options screen (Linux)	Formatted HTML text	Specifies the page text and links that prompt a user to install a new browser plug-in component. This screen provides manual download and installation options. This screen appears for Linux operating systems and browsers.
Java applet install failure screen	Formatted HTML text	Specifies the page text and links that appear when the installation of software with a Java™ applet fails. This page allows the user options to restart the session, download and manually install the software, or continue without installing software. This page appears only on non-Windows systems.
Java applet install screen	Formatted HTML text	Specifies the text that appears on a page with a Java applet to install a new browser plugin. This page appears only on non-Windows systems. Java applet install started screen on

Localizing Messages and Images in Advanced View

Name	Value	Description
		Safari® browser specifies the page text and links that appear when the Java applet is installing software. This page appears only on Macintosh® systems with the Safari web browser.
Java applet install started screen	Formatted HTML text	Specifies the page text and links that appear when the Java applet is installing software. This page appears only on non-Windows systems.

Endpoint security settings

You can customize the following settings for endpoint security messages that appear in web browsers and on mobile devices with the Customization tool.

Name	Value	Description
Antivirus check message	Text	Specifies the message displayed while the antivirus check action is checking the system.
Cache and session control ActiveX loading message	Text	Specifies the message displayed when the cache and session control ActiveX® control is loading and the user may be prompted to allow cache and session control installation.
Cache and session control ActiveX missing message	Text	Specifies the text displayed when the client requires ActiveX to start the cache and session control plug-in, and ActiveX is not available or enabled.
Cache and session control continue link	Text	Specifies the link text that the user clicks to continue when the cache and session control plug-in cannot load.
Cache and session control blocked popup message	Text	Specifies the message displayed when a popup blocker is enabled. The message includes information on how to allow popups from the BIG-IP® device. Note: We recommend that you use an HTML editor to edit the HTML code for this box. The code appears unformatted and without line breaks in the box.
Cache and session control failure message	Text	Specifies the message displayed when the cache and session control plug-in fails to start. The message includes information on possible causes. Note: We recommend that you use an HTML editor to edit the HTML code for this box. The code appears unformatted and without line breaks in the box.
Cache and session control loading message	Text	Specifies the text displayed while the cache and session control plug-in starts. Note: We recommend that you use an HTML editor to edit the HTML code for this box. The code appears unformatted and without line breaks in the box.
Checking client message	Text	Specifies the message displayed when the system is checking the client for an unspecified action.
Continue link	Text	Specifies the link text that the user clicks to continue after opening a new browser window.

Name	Value	Description
Continue without endpoint inspection message	Text	Specifies the messages displayed when client-side security checks fail. You can specify link text to cancel and link text to continue. The continue link allows the client to continue on the fallback branch.
Downloading message (appended to other messages)	Text	Specifies the message displayed while the client is downloading software components.
File check message	Text	Specifies the message displayed while the file check action is checking the system.
Firewall check message	Text	Specifies the message displayed while the firewall check action is checking the system.
Installing message (appended to other messages)	Text	Specifies the message displayed while the client is installing software.
Machine check info message	Text	Specifies the message displayed when the client is collecting machine info for the machine info check.
New browser window required message	Text	Specifies the message displayed when browser settings have changed, and the user must open a new browser window to continue.
Process check message	Text	Specifies the message displayed while the process check action is checking the system.
Virtual keyboard hide keyboard link	Text	Specifies the link text that the user clicks to hide the virtual keyboard.
Virtual keyboard label	Text	Specifies the label for the virtual keyboard.
Windows Group Policy action message	Text	Specifies the message displayed while the Windows® group policy action is configuring the system.
Windows Info check message	Text	Specifies the message displayed while the Windows information check action is checking the system.
Windows machine certificate check message	Text	Specifies the message displayed while the Windows machine certificate check action is checking the system.
Windows Protected Workspace action message	Text	Specifies the message displayed while the Protected Workspace action is starting the protected workspace.
Windows Protected Workspace continue link	Text	Specifies the link text specified that the user can click to continue without starting protected workspace.
Windows Protected Workspace continuing: extended message	Text	Specifies the message displayed when the protected workspace starts, and the system requires some time to display the protected workspace.
Windows Protected Workspace logon: short message	Text	Specifies the message displayed on the client when protected workspace resumes the logon procedure after starting.
Windows Protected Workspace started: close browser message	Text	Specifies the message displayed when protected workspace has successfully started,
Windows Registry check message	Text	Specifies the message displayed while the registry check action is checking the system.

Localizing layout and content of logout pages

Customize the layout and content of components that appear on logout pages when the access policy or user ends a session.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Expand the folders in the Customization tool navigation pane to select the framework installation item: **Customization Settings > Access Profiles > *name_of_access_profile* > Logout > General**.
5. At the top right of the customization settings pane, select the **Language** for which to customize localization messages for full and mobile browsers.
6. Customize the settings for the logout elements.
7. After you customize settings, click the **Save** icon at the top of the Customization tool.

Logout component settings

You can customize the following settings for logout messages that appear in web browsers and on mobile devices with the Customization tool.

Name	Value	Description
Access not found page reject message	Text	Specifies the message displayed when the access policy cannot be completed correctly.
Access not found page title	Text	Specifies the title for the page displayed when the access policy cannot be completed correctly.
ACL denied page reject message	Text	Specifies the message displayed when the user attempts to access a page to which access is specifically denied by an access control list.
ACL denied page return link message	Text	Specifies the link text on the ACL Denied page that the user can click to return to the previous page.
ACL denied page title	Text	Specifies the title text on the ACL Denied page.
Error message	Text	Provides a more specific error message that follows the error title, which indicates that a problem may have occurred during access policy evaluation.
Error title	Text	Specifies text that indicates that the session could not start.
New session link	Text	Specifies the text label for the hypertext link to start a new session, such as click here. This link follows the New session text.
New session text	Text	Specifies text that precedes the link a user clicks to start a new session.

Name	Value	Description
Session expired message	Text	Specifies the message that appears when the user session expires due to inactivity.
Session ID title	Text	Specifies the text that precedes the session number when an error occurs.
Success message	Text	Specifies the text displayed when the user logs out successfully.
Success title	Text	Specifies the text displayed when a session is finished.
Thank you message	Text	Specifies a thank you message displayed for network access users after logout.

Localizing error messages

Customize the error messages that appear when the client or browser encounters errors while processing the login page or running access policy sessions.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Expand the folders in the Customization tool navigation pane to select the framework installation item: **Customization Settings > Access Profiles > *name_of_access_profile* > Error Messages > *error_message_category***.
5. At the top right-side of the customization settings pane, select the **Language** for which to customize error messages for full and mobile browsers.
6. Customize the settings for the error messages.
7. After you customize settings, click the **Save** icon at the top of the Customization tool.

General error settings

You can customize the following settings for general error messages that appear in web browsers and on mobile devices with the Customization tool.

Name	Value	Description
Access denied by ACL	Text	Specifies the error displayed when an ACL entry denies access.
Client IP address changed	Text	Specifies the error displayed if the client IP address changes while the session is in progress.
Invalid Network Access resource	Text	Specifies the error displayed when the access profile cannot find a valid Network Access resource.

Localizing Messages and Images in Advanced View

Name	Value	Description
Invalid Session ID	Text	Specifies the error displayed when the Session ID is not correct. This may occur because the session has timed out.
Request error	Text	Specifies the error displayed when there is a malformed request or there is another problem with a request.
Server in maintenance mode	Text	Specifies the error displayed when a session cannot start because the server is performing maintenance.
Session ID is not found	Text	Specifies the error displayed when cookies are disabled, and this causes the session ID to be unavailable in the request.
Stateful failover couldn't be supported	Text	Specifies the error displayed when the access policy has changed and due to failover issues, the admin must log in again.
System is not licensed	Text	Specifies the error displayed when a session cannot start because the system is not licensed.
Terminated Session	Text	Specifies the error displayed when the session is terminated by the server.
Unsupported User-Agent	Text	Specifies the error displayed when the browser user agent is not supported in the policy.
User limit reached	Text	Specifies the error displayed when the resource cannot be assigned because the limit on the number of sessions has been reached.

AAA error settings

You can customize the following settings for AAA error messages that appear in web browsers and on mobile devices with the Customization tool.

Name	Value	Description
AD domain password change failure	Text	Specifies the text displayed when the attempt to change the Active Directory password failed.
AD domain password change failure with extended error	Text	Specifies the text displayed when the attempt to change the Active Directory password failed, and includes the error message from the Active Directory component.
AD domain password expired	Text	Specifies the text displayed when the Active Directory domain password has expired.
AD domain password expired with extended error	Text	Specifies the text displayed when the Active Directory password has expired, and includes the error message from the Active Directory component.
Incorrect AD username or password with extended error	Text	Specifies the text displayed when the Active Directory user name or password is incorrect, and includes the error message from the Active Directory component.
Incorrect LDAP username or password with extended error	Text	Specifies the text displayed when the LDAP user name or password is incorrect, and includes the error message from the LDAP component.

Name	Value	Description
Incorrect OAM username or password with extended error	Text	Specifies the text displayed when the OAM user name or password is incorrect, and includes the error message from the OAM component.
Incorrect RADIUS username or password with extended error	Text	Specifies the text displayed when the RADIUS user name or password is incorrect, and includes the error message from the RADIUS component.
Incorrect username or password	Text	Specifies the text displayed when the user name or password is incorrect.
OAM authentication error	Text	Specifies the text displayed when there is an OAM authentication error.
OAM authorization error	Text	Specifies the text displayed when there is an OAM authorization error.
OAM internal error	Text	Specifies the text displayed when there is an invalid setup for the OAM server.
OAM SDK initialization error	Text	Specifies the text displayed when there is an OAM error related to the F5 webgate and OAM SDK.
RADIUS challenge failure	Text	Specifies the text displayed when a RADIUS challenge fails.
RADIUS challenge failure with extended error	Text	Specifies the text displayed when a RADIUS challenge fails, and includes the error message from the RADIUS component.
SecurID logon failure with retry	Text	Specifies the text displayed when the RSA SecurID logon or password is incorrect.
SecurID logon failure with retry with extended error	Text	Specifies the text displayed when the RSA SecurID logon or password is incorrect, and includes the error message from the SecurID component.

Installation error settings

You can customize the following settings for installation error messages that appear in web browsers and on mobile devices with the Customization tool.

Name	Value	Description
ActiveX is not allowed or unsupported	Text	Specifies the error displayed when the access policy attempts to load an ActiveX® control in Microsoft® Internet Explorer® and ActiveX is not enabled.
Installation failure	Text	Specifies the error displayed when installation of a browser component fails.

Resource error settings

You can customize the following settings for resource error messages that appear in web browsers and on mobile devices with the Customization tool.

Localizing Messages and Images in Advanced View

Name	Value	Description
ACL does not exist	Text	Specifies the error text displayed when the assigned ACL does not exist.
Inconsistent host replacement string	Text	Specifies the error text displayed when portal access resources configured in Minimal Patching mode contain inconsistent host replace strings.
Incorrect resource assigned (Network Access)	Text	Specifies the error text displayed when a resource assign action is configured to assign a portal access webtop with a network access resource. Webtop and resource types must match.
Incorrect resource assigned (Portal Access)	Text	Specifies the error text displayed when a resource assign action is configured to assign a network access webtop with a portal access resource.
Invalid Dynamic ACL Assignment	Text	Specifies the error text displayed when the dynamic ACL is incorrectly assigned or configured.
Invalid host for App Tunnel resource	Text	Specifies the error text displayed when a host that the app tunnel attempts to start a connection to does not respond correctly.
Invalid host for Remote Desktop resource	Text	Specifies the error text displayed when the host that a remote desktop resource attempts to start a connection to does not respond correctly.
Invalid Portal Access start URI	Text	Specifies the error text displayed when the portal access webtop has an invalid start URI.
Invalid Static ACL assignment	Text	Specifies the error text displayed when a static ACL is not configured correctly.
Missing Network Access resource	Text	Specifies the error text displayed when a network access webtop is configured with no network access resource. Webtop and resource types must match.
More than one Network Access resource	Text	Specifies the error text displayed when more than one network access resource is assigned to an access policy branch.
Network Access and Portal Access resources assigned	Text	Specifies the error text displayed when both network access and portal access resources are assigned to an access policy branch.
Portal Access resources have inconsistent patching methods	Text	Specifies the error text displayed when multiple portal access resources are assigned to an access policy branch, with different patching methods. All portal access resources assigned to an access policy branch must use the same patching method.
Resource does not exist	Text	Specifies the error text displayed when the assigned resource does not exist.
Webtop does not exist	Text	Specifies the error text displayed when the assigned webtop does not exist.
Webtop required	Text	Specifies the error text displayed when a webtop is required, but not assigned.

Dynamic configuration error settings

You can customize the following settings for dynamic configuration error messages that appear in web browsers and on mobile devices with the Customization tool.

Name	Value	Description
Invalid Dynamic ACL entries	Text	Specifies the text displayed when a dynamic ACL contains invalid entries.

Other configuration error settings

You can customize the following settings for other errors that appear in web browsers and on mobile devices with the Customization tool.

Name	Value	Description
Unknown error	Text	Specifies the text displayed when an unknown error occurs.

Localizing logon pages

Customize the messages that appear for a specific logon page or HTTP 401 response page in an access policy.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Expand the folders in the Customization tool navigation pane to select the logon page: **Customization Settings > Access Profiles > name_of_access_profile > Access Policy > Logon Pages**.
5. Select the folder for the logon page or HTTP 401 response action.
6. Select the **General** settings.
7. At the top right of the customization settings pane, select the **Language** for which to customize logon pages.
8. Customize the settings for the logon pages.
9. After you customize settings, click the **Save** icon at the top of the Customization tool.

Logon page settings

You can customize the following settings for logon pages that appear in web browsers and on mobile devices with the Customization tool.

Localizing Messages and Images in Advanced View

Name	Value	Description
Form Header Text	Text	Specifies the text that appears at the top of the logon box.
HTTP 401 Response	Text	Specifies the text displayed when an HTTP 401 authentication error occurs.
Logon Button	Text	Specifies the text that appears on the logon button, which a user clicks to post the defined logon agents.
Logon Page Input Field # (1-5)	Text	These fields specify the text that is displayed on the logon page for each of the logon page agents, defined in the Logon Page Agent screen area.
New Password Prompt	Text	Specifies the prompt displayed when a new Active Directory password is requested.
Password and Password Verification do not Match	Text	Specifies the prompt displayed to confirm the new password when a new Active Directory password is requested.
Save Password Checkbox	Text	Specifies the text that appears adjacent to the check box that allows users to save their passwords in the logon form. This field is used only in the secure access client, and not in the web client.
Verify Password Prompt	Text	Specifies the prompt displayed to confirm the new password when a new Active Directory password is requested.

Localizing decision pages

Customize the messages that appear for decision pages.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Expand the folders in the Customization tool navigation pane to select the decision page: **Customization Settings > Access Profiles > name_of_access_profile > Access Policy > Decision Pages**.
5. Select the folder for the decision box page.
6. Select the **General** or **Advanced Customization Images** settings.
7. At the top right of the customization settings pane, select the **Language** for which to customize decision pages.
8. Customize the settings for the decision pages.
9. After you customize settings, click the **Save** icon at the top of the Customization tool.

General decision page settings

You can customize the following settings for decision pages that appear in web browsers and on mobile devices with the Customization tool.

Name	Value	Description
Field 1 Image	Image	Specifies the image that appears in the first option field on the decision page. Click the icon at the right of the field to view the image. Click Replace to change the image.
Field 2 Image	Image	Specifies the image that appears in the second option field on the decision page. Click the icon at the right of the field to view the image. Click Replace to change the image.

Advanced customization image settings

You set advanced customization images to make images you add through the image browser available to your advanced customization pages.

The **Advanced Customization Images** properties pages allow you to set advanced customization images from the image browser to associate with advanced customization image names. You can then use the image name to add an image to an advanced customization page.

To select an image from the image browser to associate with an image for advanced customization, click the button next to the current (or default) image name, and select **Replace**.

Localizing message box pages

Customize the message boxes that appear for message box pages.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Expand the folders in the Customization tool navigation pane to select the message box page:
Customization Settings > Access Profiles > *name_of_access_profile* > Access Policy > Message Pages.
5. Select the folder for the message box page.
6. Select **Advanced Customization Images** settings.
7. At the top right of the customization settings pane, select the **Language** for which to customize message pages.
8. Customize the settings for the message box pages.
9. After you customize settings, click the **Save** icon at the top of the Customization tool.

Advanced customization image settings

You set advanced customization images to make images you add through the image browser available to your advanced customization pages.

The **Advanced Customization Images** properties pages allow you to set advanced customization images from the image browser to associate with advanced customization image names. You can then use the image name to add an image to an advanced customization page.

Localizing Messages and Images in Advanced View

To select an image from the image browser to associate with an image for advanced customization, click the button next to the current (or default) image name, and select **Replace**.

Localizing ending pages

Customize the ending pages that appear in access policies.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Expand the folders in the Customization tool navigation pane to select the ending: **Customization Settings > Access Profiles > *name_of_access_profile* > Access Policy > Ending Pages**.
5. Select the folder for the message box page.
6. Select **Advanced Customization Images** settings.
7. At the top right of the customization settings pane, select the **Language** for which to customize ending pages.
8. Customize the settings for the ending pages.
9. After you customize settings, click the **Save** icon at the top of the Customization tool.

Advanced customization image settings

You set advanced customization images to make images you add through the image browser available to your advanced customization pages.

The **Advanced Customization Images** properties pages allow you to set advanced customization images from the image browser to associate with advanced customization image names. You can then use the image name to add an image to an advanced customization page.

To select an image from the image browser to associate with an image for advanced customization, click the button next to the current (or default) image name, and select **Replace**.

Chapter 8

Localizing Webtops in Advanced View

Topics:

- *What is webtop localization?*
 - *Localizing webtops*
-

What is webtop localization?

You can customize webtop settings, including the messages displayed when starting and closing the connection, and any error messages, for any language supported on the server. A webtop must be assigned to an access profile to see and customize the webtop for the languages assigned to the access profile. If you customize a webtop that is not assigned to any access profile, you can customize the default set of languages only.

Localizing webtops

Localize webtops to configure images, text, and layout for a webtop in a specific language.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Expand the folders in the Customization tool navigation pane to select page header settings, page footer settings, and other settings: **Customization Settings > Access Profiles > *name_of_access_profile* > Common**.
5. At the top right of the customization settings pane, select the **Language** for which to customize localization messages for full and mobile browsers.
6. Click **Page Header Settings** to provide a customized disconnection message.
7. Click **Page Footer Settings** to provide a customized footer for access profile pages.
8. Click **Other Settings** to configure the following settings.

Options	Description
JavaScript disabled warning	Specifies the warning when JavaScript is not enabled in the browser.
New session link	Specifies the link text to start a new session.
New session text	Specifies the text that appears before the new session link.

9. After you customize settings, click the **Save** icon at the top of the Customization tool.

Webtop form and message settings

You can customize the following settings for form and message settings that appear on webtops, in web browsers and on mobile devices, with the Customization tool.

Name	Value	Description
App Tunnels conflict with Network Access message	Text	Specifies the message that appears when an application tunnel is open and the user attempts to start a network access tunnel.
Connected message	Text	Specifies the message displayed on the login screen when the client is connected.
Connecting message	Text	Specifies the message displayed on the login screen when the client is connecting.
Connection already established error message	Text	Specifies the message displayed when a connection is already established.
Connection closed by server error message	Text	Specifies the error message displayed when an error occurs on the server, and causes the session to fail. Check the log files for more specific information.
Connection dropped error message	Text	Specifies the message displayed when an error occurs, and the connection is dropped. Check the log files for more specific information.
Connection failed to start error message	Text	Specifies the message displayed when the connection cannot start. Check the log files for more specific information.
Connection to server could not start error message	Text	Specifies the error message displayed when the client cannot make a connection to the server. Check the log files for more specific information.
Disconnected due to configuration error message	Text	Specifies the error displayed when a configuration error causes the session to stop and the client to be disconnected.
Disconnected message	Text	Specifies the message displayed on the login screen when the client is disconnected.
Downloading progress bar (caption)	Text	Specifies the caption displayed above the progress bar when client components are downloading.
F5 plug-in not installed or incompatible plug-in error message	Text	Specifies the error message displayed when the F5 plug-in is not installed or is incompatible with the current server. This error occurs on Macintosh® and Linux clients only.
Failed message	Text	Specifies the message displayed on the login screen when the connection fails.
Initialization message	Text	Specifies the message displayed on the login screen when the login sequence is initializing.
Installation error pppd daemon not found in /usr/sbin directory (mac/linux)	Text	Specifies the error message displayed when the pppd daemon cannot start. This error occurs on Macintosh and Linux clients only.
Installation message	Text	Specifies the message displayed on the login screen when the login sequence is installing software.
Loading message	Text	Specifies the message displayed on the login screen when the login sequence is starting installed software.
Network Access client internal error message	Text	Specifies the message displayed when an internal client error occurs and causes the network access session to fail. Check the log files for more specific information.

Localizing Webtops in Advanced View

Name	Value	Description
Network Access conflict with App Tunnels message	Text	Specifies the message that appears when a network access tunnel is open and the user attempts to start an app tunnel.
Plugin installation incomplete error message	Text	Specifies the message displayed when the F5 plugin is not installed correctly. This error occurs on Linux clients only.
pppd daemon did not start error message (mac/linux)	Text	Specifies the error message displayed when the pppd daemon cannot start. This error occurs on Macintosh and Linux clients only.
Queued message	Text	Specifies the message displayed on the login screen when the client is queued to make a connection.
Reconnecting message	Text	Specifies the message displayed on the login screen when the client is reconnecting.
Request local credentials during linux installation	Text	<p>Specifies the code that creates a local credentials request screen. This is required for Linux systems only. We recommend that you edit this code in an HTML editor to make the layout easier to view.</p> <hr/> <p> Note: Do not add manual line breaks to the webtop form; this causes errors. Use the
 tag to add a line break to the code.</p> <hr/>
Routing table change caused disconnect error message	Text	Specifies the error displayed when a change to the client routing table causes the session to stop and the client to be disconnected.
Secure connection stopped message	Text	Specifies the message displayed when the secure connection is stopped by the client. Check the log files for more specific information.
Toolbar text	Text	Specifies the text that appears in the webtop toolbar.

BIG-IP Edge Client webtop settings

You can customize the following settings for the BIG-IP® Edge Client® webtop, in web browsers and on mobile devices, with the Customization tool.

Name	Value	Description
Connection Established notification	Text	Specifies the message that appears in the BIG-IP Edge Client when a connection is established.
Disconnected due to configuration error notification	Text	Specifies the message displayed in the BIG-IP Edge Client when the connection is closed due to a configuration error.
New BIG-IP Edge Client available message	Text	Specifies the message displayed during connection, when a newer version of the BIG-IP Edge Client is available from the server.

Name	Value	Description
Routing table change causes disconnect notification	Text	Specifies the message displayed when a change in the routing table on the client machine causes the client to disconnect.

Settings for showing and hiding information on webtops

You can customize the following show and hide settings for the webtop, in web browsers and on mobile devices, with the Customization tool.

Name	Value	Description
Disable logging link	Text	Specifies the link text to disable logging.
Enable logging link	Text	Specifies the link text to enable logging.
Hide label in table caption link	Text	Specifies the text on the webtop screen that the user clicks to hide a table caption.
Show IP address configuration link	Text	Specifies the text on the webtop screen that the user clicks to show the IP address configuration.
Show label in table caption link	Text	Specifies the text on the webtop screen that the user clicks to show a table caption.
Show log file link	Text	Specifies the text on the secure access screen that the user clicks to show the log file.
Show routing table link	Text	Specifies the text on the webtop screen that the user clicks to show the routing table.
Status element	Text	Specifies the text on the webtop screen that heads the status section.

Webtop logout and relaunch settings

You can customize the following settings for logout and relaunch messages that appear on webtops, in web browsers and on mobile devices, with the Customization tool.

Name	Value	Description
Logout link	Text	Specifies the link text on the webtop screen that the user clicks to log out.
Relaunch applications link	Text	Specifies the link text on the webtop screen that the user clicks to restart the applications that are defined in the network access launch applications section.

Webtop activity section setting

You can customize the following setting for the activity section.

Localizing Webtops in Advanced View

Name	Value	Description
Activity section caption	Text	Specifies the caption for the section that shows client and server activity.

Webtop new session settings

You can customize the following settings for new sessions on the webtop.

Name	Value	Description
New session link	Text	Specifies the link text on the webtop screen that the user clicks to start a new session.
New session text	Text	Specifies the text that precedes the new session link.

Webtop web applications session timeout settings

You can localize the timeout settings for portal access applications that are displayed on the webtop.

Name	Value	Description
Header message (idle timeout)	Text	Specifies the message displayed when the idle timeout is reached for a portal access session.
Header message (maximum timeout)	Text	Specifies the message displayed when the maximum session time timeout is reached for a portal access session.
Postfix text for 'remaining time' message (idle timeout)	Text	Specifies the text after the seconds display in the remaining time warning for a portal access idle timeout.
Postfix text for 'remaining time' message (maximum timeout)	Text	Specifies the text after the seconds display in the remaining time warning for a portal access maximum session time timeout.
Postfix text for seconds in 'remaining time' message (idle timeout)	Text	Specifies the text after the number of seconds remaining when an idle timeout is reached.
Postfix text for seconds in 'remaining time' message (maximum timeout)	Text	Specifies the text after the number of seconds remaining when a maximum session time timeout is reached.
Prefix text for 'remaining time' message (idle timeout)	Text	Specifies the message displayed before the seconds and postfix message display in the remaining time warning for a portal access idle timeout.
Prefix text for 'remaining time' message (maximum timeout)	Text	Specifies the text before the seconds and postfix message display in the remaining time warning for a portal access maximum session time timeout.
Prefix text for seconds in 'remaining time' message (idle timeout)	Text	Specifies the text displayed before the number of seconds remaining when an idle timeout is reached.

Name	Value	Description
Prefix text for seconds in 'remaining time' message (maximum timeout)	Text	Specifies the text displayed before the number of seconds remaining when a maximum session time timeout is reached.
Text for 'disconnect' button	Text	Specifies the text on the button that the user clicks to disconnect the session.
Text for 'disconnect' button tooltip	Text	Specifies the tooltip text for the button that the user clicks to disconnect the session.
Text for 'stay connected' button (idle timeout)	Text	Specifies the text on the button that the user clicks to stay connected to the session in the event of an idle timeout.
Text for 'stay connected' button (maximum timeout)	Text	Specifies the text on the button that the user clicks to stay connected to the session in the event of a maximum session time timeout.
Text for 'stay connected' button tooltip (idle timeout)	Text	Specifies the tooltip text for the button that the user clicks to stay connected to the session in the event of an idle timeout.
Text for 'stay connected' button tooltip (maximum timeout)	Text	Specifies the tooltip text for the button that the user clicks to stay connected to the session in the event of a maximum session time timeout.

Webtop hometab settings

You can localize the timeout settings for portal access applications that are displayed on the webtop.

Name	Value	Description
Home image text	Text	Specifies the text for the home image on the hometab.
Home link text	Text	Specifies the text for the home link.
Postfix text for 'remaining time' message (idle timeout)	Text	Specifies the text after the seconds display in the remaining time warning for a portal access idle timeout.
Postfix text for 'remaining time' message (maximum timeout)	Text	Specifies the text after the seconds display in the remaining time warning for a portal access maximum session time timeout.
Postfix text for seconds in 'remaining time' message (idle timeout)	Text	Specifies the text after the number of seconds remaining when an idle timeout is reached.
Postfix text for seconds in 'remaining time' message (maximum timeout)	Text	Specifies the text after the number of seconds remaining when a maximum session time timeout is reached.
Prefix text for 'remaining time' message (idle timeout)	Text	Specifies the message displayed before the seconds and postfix message display in the remaining time warning for a portal access idle timeout.

Localizing Webtops in Advanced View

Name	Value	Description
Prefix text for 'remaining time' message (maximum timeout)	Text	Specifies the text before the seconds and postfix message display in the remaining time warning for a portal access maximum session time timeout.
Prefix text for seconds in 'remaining time' message (idle timeout)	Text	Specifies the text displayed before the number of seconds remaining when an idle timeout is reached.
Prefix text for seconds in 'remaining time' message (maximum timeout)	Text	Specifies the text displayed before the number of seconds remaining when a maximum session time timeout is reached.
Text for 'disconnect' button	Text	Specifies the text on the button that the user clicks to disconnect the session.
Text for 'disconnect' button tooltip	Text	Specifies the tooltip text for the button that the user clicks to disconnect the session.
Text for 'stay connected' button (idle timeout)	Text	Specifies the text on the button that the user clicks to stay connected to the session in the event of an idle timeout.
Text for 'stay connected' button (maximum timeout)	Text	Specifies the text on the button that the user clicks to stay connected to the session in the event of a maximum session time timeout.
Text for 'stay connected' button tooltip (idle timeout)	Text	Specifies the tooltip text for the button that the user clicks to stay connected to the session in the event of an idle timeout.
Text for 'stay connected' button tooltip (maximum timeout)	Text	Specifies the tooltip text for the button that the user clicks to stay connected to the session in the event of a maximum session time timeout.

Full webtop settings

You can localize particular messages and links for full webtops.

Name	Value	Description
Applications and links	Text	Specifies the header text for the applications and links section on the full webtop.
Empty URL input message	Text	Specifies the text in the empty URL field on the full webtop.
Header message	Text	Specifies the header message for the full webtop.
Help window contents	Text/HTML	Specifies the help text in the help window. Click the edit button to the right of this field to see the full text.
Help window contents header	Text	Specifies the header for the Help window.
Network access	Text	Specifies the text for the network access section.
Toolbar - help	Text	Specifies the help link text on the toolbar.

Full webtop popup window settings

You can localize particular messages and links for full webtops.

Name	Value	Description
Action label	Text	Specifies the label for the action section on the webtop popup.
Application Name label	Text	Specifies the label for the application name section on the webtop popup.
Application Tunnels label	Text	Specifies the label for the application tunnels section on the webtop popup.
Connected to message	Text	Specifies the text for the tunnel or resource the user is connected to, on the webtop popup.
Logged in as message	Text	Specifies the label for the user name that the user is logged in as on the webtop popup.
Network access label	Text	Specifies the label for the network access section.
Optimized Applications label	Text	Specifies the label for the optimized applications section.
Page title	Text	Specifies the page title for the popup window.
Status label	Text	Specifies the text for the status label on the popup window.
Summary label	Text	Specifies the text for the label for the summary section on the popup window.
Terminate All Tunnels button	Text	Specifies the text for the button to stop all tunnel connections.
Terminate button	Text	Specifies the text for the Terminate button for a specific connection.
Terminate NA Tunnels button	Text	Specifies the text for the button to stop the network access connection.
Total Traffic label	Text	Specifies the label for the total traffic display.
Traffic compression label	Text	Specifies the label for the traffic compression display.
Traffic label	Text	Specifies the label for the traffic display.
Traffic Received label	Text	Specifies the label for received traffic section.
Traffic Received label	Text	Specifies the label for received traffic section.
Traffic Sent label	Text	Specifies the label for sent traffic section.
Traffic Type label	Text	Specifies the label for the traffic type section.
View label	Text	Specifies the label for the view section.
Warning before closing popup	Text	Specifies the warning that appears before closing the popup window and closing all connections.

Localizing Webtops in Advanced View

Name	Value	Description
Warning when user navigated from Webtop	Text	Specifies the warning that appears when the user attempts to navigate away from the webtop and close connections.
Warning when Webtop closed	Text	Specifies the warning when the webtop popup is closed and connections are to be closed.

Full webtop Citrix logon form settings

You can localize settings for the Citrix® logon form on the webtop.

Name	Value	Description
Cancel button text	Text	Specifies the text for the cancel button on the Citrix logon form.
Domain label	Text	Specifies the label for the domain field on the Citrix logon form.
Logon button text	Text	Specifies the text on the logon button on the Citrix logon form.
Logon form caption	Text	Specifies the text for the Citrix logon form caption.
Logon form caption when logon fails	Text	Specifies the text to display when Citrix logon fails.
Message to show to the user when connection to Citrix server fails	Text	Specifies the text to display when the Citrix connection fails, and a retry or cancel option is presented.
Message to show to the user when logon to Citrix server fails	Text	Specifies the text to display when the logon to the Citrix server fails, and a retry or cancel option is presented.
Password label	Text	Specifies the label for the password field.
Try again button text	Text	Specifies the text for the retry button when the Citrix logon or connection fails.
Username label	Text	Specifies the text for the label for the username field.

Full webtop Citrix installer settings

You can localize settings for the Citrix® installer on the webtop.

Name	Value	Description
Citrix client not detected caption	Text	Specifies the caption when the Citrix client is not detected by the installer.
Citrix client not detected message	Text	Specifies the message when the Citrix client is not detected by the installer, and provide instructions to download the installer.
Citrix client not up-to-date caption	Text	Specifies the text when a newer Citrix client is available for download.

Name	Value	Description
Citrix client not up-to-date message	Text	Specifies the message when a newer Citrix client is available for download, and provides instructions to download an updated client.
Download button text	Text	Specifies the label on the download button.
Skip installation button text	Text	Specifies the label on the button to skip installation.

Full webtop Citrix browser setting

You can localize settings for the Citrix® browser on the webtop.

Name	Value	Description
Close browser	Text	Specifies the text to close the Citrix browser.

Chapter 9

Localizing Captions for Resources in Advanced View

Topics:

- *What is resource caption localization?*
 - *Localizing captions*
-

What is resource caption localization?

With caption localization, you can change the caption and description for resources on the webtop.

Localizing captions

Localize webtops to configure captions and descriptions for resources on a full webtop in a specific language.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. Click the Localization tab.
5. Select the resource type folder for **App Tunnels, Network Access, Remote Desktops, Portal Access, or Webtop Links**.
6. Select the resource name.
7. At the top right of the customization settings pane, select the **Language** for which to customize the caption and description for full and mobile browsers.
8. Type a **Caption** to provide a label for the resource on the full webtop.
9. Type a **Detailed Description** to provide a detailed description for the resource in the full webtop.
10. After you customize settings, click the **Save** icon at the top of the Customization tool.

Chapter 10

Changing Customized Properties with Advanced Edit Mode

Topics:

- [What is Advanced Edit Mode customization?](#)

What is Advanced Edit Mode customization?

With advanced customization, you can directly edit PHP, CSS, JavaScript, and HTML to control the display and function of web and client pages in Access Policy Manager. You can use the built-in editor to edit files, or you can copy and paste with an editing application of your choice.

Editing files in Advanced Edit Mode

Edit files in Advanced Edit Mode to configure settings not easily set with the Properties Edit Mode.

1. On the Main tab, click **Access Policy > Customization**.
The Customization tool appears, in Basic Customization view.
2. From the View list, select **Advanced Customization**.
The Customization tool switches to Advanced (tree) view.
3. In Advanced Customization view, from the **Form Factor** menu at the top of the Customization tool, select **Full/Mobile Browser**.
4. In Advanced Customization view, from the **Edit Mode** menu at the top of the Customization tool, select **Advanced**.
5. Select the resource type folder for **Access Profiles** or **Webtops**.
6. Navigate through the folder hierarchy to find the file you want to edit, and click on the file.
The file appears in the built-in editor pane, with simple syntax highlighting.
7. Make the changes you require to the file. You can make changes in the editor window, or you can edit in an external editor using copy and paste commands for your operating system.
 - To save a draft of your changes without applying them, click the **Save Draft** button.
 - To discard any changes saved with the **Save Draft** button, click **Revert**, and follow the instructions on the confirmation dialog.
8. After you customize settings, click the **Save** icon at the top of the Customization tool.

Properties for access profiles in Advanced Edit Mode

You can customize the following files for access profiles in Advanced Edit Mode.

Name	Location	Description
apm_edge.css	Customization Settings > Access Profiles > <i>access_profile</i> > Common	The CSS that controls the look and feel for BIG-IP® Edge Client® pages.
header.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Common	Specifies the page header content for access profile pages on all devices.
apm_mobile_ppc.css	Customization Settings > Access Profiles > <i>access_profile</i> > Common	The CSS that controls the look and feel for pages on a PocketPC device.
javascript_disabled.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Common	The layout for the page that appears when JavaScript is disabled on the client.

Name	Location	Description
apm_mobile.css	Customization Settings > Access Profiles > <i>access_profile</i> > Common	The layout properties for access policy pages on any mobile device that is not a PocketPC.
apm_full.css	Customization Settings > Access Profiles > <i>access_profile</i> > Common	The CSS and PHP code that controls the look and feel for pages on a web browser.
footer.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Common	The include that specifies the footer text line.
apm.css	Customization Settings > Access Profiles > <i>access_profile</i> > Common	The PHP code that determines the CSS file that is used with a particular browser or device.
access_notfound.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Logout	The HTML, JavaScript, and PHP code that presents a page when access is not granted.
logout.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Logout	The HTML, JavaScript, and PHP code that presents a page when the user logs out. The file includes several options for different logout reasons.
my.acl.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Logout	The HTML, JavaScript, and PHP code that presents a page when the access to a page is denied for one of several reasons, including by an ACL.
http_401.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Access Policy > Logon Pages > <i>logon_page</i>	The page that appears when an HTTP 401 error (unauthorized) occurs.
logon.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Access Policy > Logon Pages > <i>logon_page</i>	A PHP file that specifies the layout and items that appear on the logon page.
decision_box.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Access Policy > Decision Pages > <i>decision_box</i>	Specifies the layout for the HTML that appears in a decision box.
message_box.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Access Policy > Message Pages > <i>message_box</i>	Specifies the layout for the HTML that appears in a message box.
access_notfound.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Access Policy > Ending Pages > <i>ending</i>	The HTML page that appears when access cannot be established.
logout.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Access Policy > Ending Pages > <i>ending</i>	The HTML page that appears when session logout occurs for one of several reasons.
my.acl.inc	Customization Settings > Access Profiles > <i>access_profile</i> > Access Policy > Ending Pages > <i>ending</i>	The HTML page that appears when access is denied because of a login failure or ACL issue.

Changing Customized Properties with Advanced Edit Mode

Name	Location	Description
Macro pages	Customization Settings > Access Profiles > <i>access_profile</i> > Macros > <i>macro</i>	Macros can include any of the login page, decision page, and message page customization files as listed here.

Properties for webtops in Advanced Edit Mode

You can customize the following files for webtops in Advanced Edit Mode.

Name	Location	Description
webtop_popup.css	Customization Settings > Webtops > <i>webtop</i>	The CSS that controls the look and feel for the webtop popup window.
desktopClass.js.inc	Customization Settings > Webtops > <i>webtop</i>	The JavaScript code that specifies how the webtop page is dynamically created.
webtop_help.inc	Customization Settings > Webtops > <i>webtop</i>	The HTML code on the webtop page that provides the link to the webtop help page.
hometab.inc	Customization Settings > Webtops > <i>webtop</i>	The JavaScript code that controls the look and feel for the Home Tab.

Index

A

- access policy
 - customizing page appearance 31
 - decision page settings 56
 - logon page settings 55
 - personalizing 31
- access policy items
 - settings 31
- access policy pages
 - properties 31
- access profile
 - AAA error settings 52
 - basic settings 14
 - branding settings for fonts 27
 - branding settings for form 29
 - branding settings for form elements 30
 - branding settings for general page style 27
 - branding settings for image 29
 - branding settings for layout 28
 - branding settings for page footers 28
 - branding settings for page headers 27
 - browser framework settings 47
 - customizing appearance 26
 - dynamic configuration error settings 55
 - endpoint security settings 48
 - general error settings 51
 - installation error settings 53
 - logout page settings 50
 - personalizing 26
 - resource error settings 53
 - settings for advanced customization images 30, 31, 42, 57, 58
 - unknown error settings 55
- access profile pages
 - customizing appearance 26
- activity section
 - webtop setting 63
- advanced customization images
 - setting for pages 30, 31, 42, 57, 58
- advanced edit mode
 - editing files 74
- Advanced Edit Mode
 - editing CSS 74
 - editing JavaScript 74
 - editing PHP 74
 - files for access profiles 74
 - files for webtops 76
- app tunnel
 - basic settings 15

B

- basic customization
 - access profile 14

- basic customization (*continued*)

- app tunnel 15
- network access 16
- portal access 17
- remote desktop 16
- webtop link 17
- webtop settings 16

- Basic customization
 - starting 14

- Basic Customization view 14

- BIG-IP Edge Client

- branding 20, 21
- localization 22, 32
- localizing webtop settings 62
- webtop settings 62

- branding

- customizing access profiles 26
- customizing for BIG-IP Edge Client 20
- customizing for logout pages 30
- customizing for webtops 36
- customizing front login page image 31
- for BIG-IP Edge Client 21
- settings for advanced customization images 30, 31, 42, 57, 58
- settings for appearance 27
- settings for fonts 27
- settings for form 29
- settings for form elements 30
- settings for image 29
- settings for layout 28
- settings for page footers 28
- settings for page headers 27

C

- Citrix

- browser setting for full webtop 69
- installer settings for full webtop 68
- settings for full webtop 68

- common pages

- localizing 46

- common page styles

- customizing settings 14

- connectivity status

- setting icons 36

- CSS files

- for access profiles 74
- for webtops 76

- CSS sprites image

- setting 36

- customization

- editing in Advanced Edit Mode 74
- for BIG-IP Edge Client 20
- for full and mobile browsers 26
- form factors 12

Index

- customization (*continued*)
 - for webtops 36
 - overview 12
- Customization
 - tool 12
- Customization tool
 - starting 12
- customized pages
 - preview 21, 22, 26, 32
- customizing
 - basic settings 14
 - by editing files 74
- customizing decision box pages 31
- customizing ending pages 31
- customizing message box pages 31

D

- decision box pages
 - customizing appearance 31
 - localizing 56
- decision pages
 - localizing 56
 - localizing in access policy 56
 - settings in access policy 56

E

- Edge Client
 - localizing webtop settings 62
 - webtop settings 62
- ending pages
 - customizing appearance 31
 - localizing 58
- endpoint security
 - localizing messages 48
 - settings 48
- error messages
 - AAA settings 52
 - dynamic configuration settings 55
 - general settings 51
 - installation settings 53
 - localizing 51
 - localizing AAA error messages 52
 - localizing dynamic configuration error messages 55
 - localizing general errors 51
 - localizing in access profiles 51
 - localizing installation error messages 53
 - localizing other error messages 55
 - localizing resource error messages 53
 - other error settings 55
 - resource settings 53

F

- fonts
 - settings for access profiles 27
- form
 - settings for access profiles 29

- form and message settings
 - localizing for webtops 60
- form appearance
 - settings for access profiles 30
- form factors
 - for customization 12
- framework
 - localizing 46, 50
 - settings 47
- full and mobile browser
 - branding for access policy items 31
- full webtop
 - appearance settings 41
 - Citrix browser setting 69
 - Citrix installer settings 68
 - Citrix logon settings 68
 - company logo 42
 - localize settings 66
 - popup window settings 67
- full webtops
 - localizing images 44
 - localizing resource captions 72

H

- hide
 - localizing webtop settings 63
 - webtop settings 63
- hometab
 - configuration settings 38

I

- image
 - adding a company logo 42
 - settings for access profiles 29
- image browser
 - adding images 20
- images
 - adding with the image browser 20
 - localizing for webtops 60

J

- JavaScript files
 - for access profiles 74
 - for webtops 76

L

- layout
 - settings for access profiles 28
- localization
 - customizing for BIG-IP Edge Client 22, 32
 - for access policy items 31
 - for BIG-IP Edge Client 22, 32
 - for common pages 46
 - for resource captions 72
 - for webtops 60

- localization (*continued*)
 - of decision pages 56
 - of ending pages 58
 - of error messages 51
 - of logon page 46
 - of logon pages 55
 - of loout page 50
 - of message box pages 57
- localizing images
 - for webtops 60, 72
- localizing messages
 - for full and mobile browsers 46
 - for webtops 60, 72
- login form
 - personalizing 29
- login form appearance
 - personalizing 30
- login pages
 - customizing appearance 31
- logon page
 - localizing layout and content 46
- logon pages
 - localizing 55
 - localizing in access policy 55
 - settings in access policy 55
- logout
 - customizing 30
 - webtop settings 63
- logout page
 - localizing layout and content 50
- logout pages
 - localizing messages 50
 - settings 50

M

- message box pages
 - customizing appearance 31
 - localizing 57
- messages
 - localizing 32
 - localizing for common pages 46

N

- network access
 - basic settings 16
- new sessions
 - webtop settings 64

P

- page footers
 - settings for access profiles 28
- page headers
 - settings for access profiles 27
- pages
 - localizing in access profiles 46, 50

- personalization
 - for resource images 44
- personalizing
 - images for resources 44
- personalizing images
 - for webtops 44
- PHP files
 - for access profiles 74
 - for webtops 76
- portal access
 - basic settings 17
 - timeout settings 64, 65
- portal access hometab
 - configuration settings 38
- portal access timeout
 - configuration settings 37
- preview customization changes 21, 22, 26, 32

Q

- quick start 14
 - access profile customization settings 14
 - app tunnel customization settings 15
 - network access customization settings 16
 - portal access customization settings 17
 - remote desktop customization settings 16
 - using for customization 14
 - webtop common customization settings 16
 - webtop link customization settings 17

R

- relaunch
 - webtop settings 63
- remote desktop
 - basic settings 16

S

- show
 - localizing webtop settings 63
 - webtop settings 63
- starting the Customization tool 12

T

- timeout
 - webtop settings 64, 65
- timeout window
 - configuration settings 37
- tool
 - for customization 12

V

- views
 - Basic 14
 - for customization 12

Index

W

- web applications
 - timeout settings 64, 65
- web browsers
 - customizing access profile logout 30
- webtop
 - activity setting 63
 - appearance settings 41
 - basic settings 16
 - connectivity status icons 36
 - CSS sprites image 36
 - form settings 60
 - full webtop Citrix browser setting 69
 - full webtop Citrix installer settings 68
 - full webtop Citrix settings 68
 - full webtop popup settings 67
 - full webtop settings 66
- webtop (*continued*)
 - logout settings 63
 - message settings 60
 - new session settings 64
 - portal access hometab settings 38
 - portal access session timeout settings 64, 65
 - portal access timeout settings 37
 - relaunch settings 63
 - settings for BIG-IP Edge Client 62
 - showing information settings 63
- webtop customization 44
- webtop customization 60, 72
- webtop link
 - basic settings 17
- webtops
 - customizing appearance 36
 - localizing 60
 - personalizing 36